

How to set up TensorFlow in a micromamba environment

Using micromamba

```
mm create -p ./env -y tensorflow
mm activate ./env

# executable stack needed to be cleared on Slackware
patchelf --clear-execstack $CONDA_PREFIX/lib/libtensorflow_cc.so.2

# make sure GPU is recognized
python -c "import tensorflow as tf;
print(tf.config.list_physical_devices('GPU'))"
```

Using PyPI

```
# the latest tensorflow supports python 3.13
mm create -p ./env -y python=3.13
mm activate ./env

# add cuda lib paths to LD_LIBRARY_PATH automatically when activating the
# environment
mkdir -p $CONDA_PREFIX/etc/conda/activate.d
cat > $CONDA_PREFIX/etc/conda/activate.d/tensorflow-cuda.sh <<'EOF'
export _OLD_LD_LIBRARY_PATH="$LD_LIBRARY_PATH"

export LD_LIBRARY_PATH="$(python - <<'PY'
import site
from pathlib import Path

for sp in site.getsitepackages():
    nvidia = Path(sp) / "nvidia"
    if nvidia.exists():
        for lib in nvidia.glob("*/lib"):
            print(lib, end=":")

PY
)$LD_LIBRARY_PATH"
EOF

mkdir -p $CONDA_PREFIX/etc/conda/deactivate.d
cat > $CONDA_PREFIX/etc/conda/deactivate.d/tensorflow-cuda.sh <<'EOF'
export LD_LIBRARY_PATH=$_OLD_LD_LIBRARY_PATH
EOF
```

```
pip install tensorflow[and-cuda]

. $CONDA_PREFIX/etc/conda/activate.d/tensorflow-cuda.sh

# make sure GPU is recognized
python -c "import tensorflow as tf;
print(tf.config.list_physical_devices('GPU'))"
```

From:
<https://hydrowiki.isnew.info/> - HydroCS Wiki

Permanent link:
https://hydrowiki.isnew.info/howtos/how_to_set_up_tensorflow_in_a_micromamba_environment

Last update: 2026-06-17 07:26 pm

